Reporting Limit (RL)

Presenter

Chung-Rei Mao, Ph.D.

Chemist, Environmental and Munitions Center of Expertise

US Army Engineering and Support Center Huntsville, AL

31 March 2011





US Army Corps of Engineers
BUILDING STRONG®





a. REPORT unclassified	b. ABSTRACT unclassified	c. THIS PAGE unclassified	Same as Report (SAR)	30		
16. SECURITY CLASSIFIC		17. LIMITATION OF ABSTRACT	18. NUMBER OF PAGES	19a. NAME OF RESPONSIBLE PERSON		
15. SUBJECT TERMS						
14. ABSTRACT						
Presented at the 20 1 Apr, Arlington, V	11 DoD Environme	ntal Monitoring &	Data Quality Wo	rkshop (EMI	OQ 2011), 28 Mar ?	
12. DISTRIBUTION/AVAILABILITY STATEMENT Approved for public release; distribution unlimited						
				11. SPONSOR/MONITOR'S REPORT NUMBER(S)		
9. SPONSORING/MONITORING AGENCY NAME(S) AND ADDRESS(ES)				10. SPONSOR/MONITOR'S ACRONYM(S)		
7. PERFORMING ORGANIZATION NAME(S) AND ADDRESS(ES) US Army Engineering and Support Center, P.O. Box 1600 ,Huntsville, AL, 32807				8. PERFORMING ORGANIZATION REPORT NUMBER		
				5f. WORK UNIT NUMBER		
				5e. TASK NUMBER		
6. AUTHOR(S)				5d. PROJECT NUMBER		
				5c. PROGRAM ELEMENT NUMBER		
4. TITLE AND SUBTITLE Reporting Limit (F		5a. CONTRACT NUMBER 5b. GRANT NUMBER				
1. REPORT DATE 31 MAR 2011		2. REPORT TYPE		3. DATES COVE 00-00-2011	ERED 1 to 00-00-2011	
maintaining the data needed, and of including suggestions for reducing	lection of information is estimated to completing and reviewing the collecti- this burden, to Washington Headqu- uld be aware that notwithstanding an DMB control number.	ion of information. Send comments arters Services, Directorate for Info	regarding this burden estimate or ormation Operations and Reports	or any other aspect of the control o	his collection of information, Highway, Suite 1204, Arlington	

Report Documentation Page

Form Approved OMB No. 0704-0188

Purpose

- What is Reporting Limit (RL)?
- Why is RL needed?
- How is RL established?
- Applications and case study
- Major issues
- Summary



Introduction

- Reporting Limit (RL) is widely used but not clearly defined. For example:
 - RL the minimum value below which data are documented as non-detects – EPA OW, Office of Resource Conservation and Recovery (ORCR), and Office of Enforcement and Compliance Assurance (OECA)
 - > RL the minimum value of the calibration range. Analyte detections between the detection limit and the reporting limit are reported as estimated EPA ORD and ORCR
 - RL > MDL and the client and/or data-users determine RL
 California Department of Health
- Many projects improperly set RL at contract lab's LOQ

RL in DoD QSM

- DoD QSM Version 4.2:
 - RL a client-specified lowest concentration value that meets project requirements for quantitative data with known precision and bias for a specific analyte in a specific matrix
 - RL = Client-specified quantitation limit that meets project data quality needs
 - > RL is clearly defined in the DoD QSM but
 - without determination procedure




Project-Specific RL

- Why is a Project-Specific RL needed?
 - > To reliably determine if a site is CLEAN
 - ✓ CLEAN: [X] < Regulatory Level, Background Level, Risk-Based Level, etc., i.e., Action Level (AL)
 - ✓ Procedure: comparison of [X], mean, etc. with AL
 - ✓ Need to determine or estimate true analyte concentration with uncertainty at Project-Specific RL (i.e., Decision Level)
 - > To select analytical methods and labs




May RL = AL?

- To reliably determine if a site is clean, one needs to determine if [X] < AL
- Problems with RL = AL



Is [X] < AL?


• Is [X] < AL? [X] = single/multi-measurements




Need Quantitation at RL < AL

- To determine if [X] < AL, one needs to quantify [X] at Project-Specific RL
- Project-Specific RL depends on:
 - AL (regulatory level, background, risk-based, etc.)
 - Data Quality (precision & bias)
 - Tolerable Decision Errors (FP/FN, Type I/II)
- RL < AL but how much lower depends on Data Quality and Tolerable Decision Errors

Data Quality - Precision



Tolerable Decision Error - FP



RL vs. AL, DQ, & TDE

Project-Specific RL depends on:

```
    > RL < AL</li>
    > RL ↓ if Data Quality (DQ) ↓
    > RL ↓ if Tolerable Decision Errors (TDE) ↓
```

How to establish a Project-Specific RL?



How's RL Commonly Established?

RL = Lab's LOQ (~ 80% projects)



RL = Lab's MDL

RL = Regulatory Limit

RL = 3 − 5 times less than AL



Common Reasons for Lack of Project-Specific RL

- Don't know how
- Unknown data quality before analysis
- Huge field sampling errors
- Risk assessor establishes
 - > PMs believe RL in number is adequate
- Limited resources
- Pandora's box




Inputs for Establishing Project-Specific RL

- Action Level (AL): Regulatory level, background level, risk-based level, etc.
- Anticipated Data Quality: Based on DQOs, historical data, method, publication, etc.
- Tolerable Decision Errors: Type I/II (α/β) or FP/FN (Default $\alpha = \beta = 0.05$ or FP = FN = 5%)



Procedure for Establishing RL

 H_0 : X > AL, H_A : X \leq AL; decision errors $\alpha = \beta = 0.05$



 $RL \le (AL - \Delta) \times \%R = (AL - k \times RSD \times AL) \times \%R$, where k = Error Factor, RSD = Rel Std Dev, %R = Recovery

Determine n, RSD, & %R

- $RL \leq (AL k \times RSD \times AL) \times \%R$
 - > k = 4 if FP = FN = 5% (2 RSD + 2 RSD)
 - k = 5 if FP = 1% (3 RSD) & FN = 5% (2 RSD)
 - > k = 6 if FP = FN = 1% (3 RSD + 3 RSD)
- $RSD \le [1 RL / (AL \times \%R)] / k$
 - If k = 4, RSD must be < 25%</p>
 - \rightarrow If k = 5, RSD must be < 20%
 - \rightarrow If k = 6, RSD must be < 17%

k is based on tolerable decision errors RSD & %R are data quality indicators at RL



Determine AL, DQ, & TDEs

- Action Level (AL): Regulatory level, background, risk-based level, etc.
- Anticipated Data Quality: Based on DQOs, historical data, method, publication, etc.
 - > Historical data
 - > DoD QSM LCS Control Limits
 - > Technology capabilities
- Tolerable Decision Errors: Type I/II (α/β)
 - > Regulations
 - > Practicality
 - > Resources



Applications of RL

- Select analytical methods
 - > RL vs. method performance
- Select analytical labs
 - > RL vs. lab performance
- Assess data quality
 - Lab LOQ vs. project RL (LOQ ≤ RL if compatible precision and bias)
- Assess data usability
 - Lab LOQ vs. project RL and AL (LOQ ≤ RL < AL if compatible precision and bias)</p>


Case Study of Project-Specific RL

- Investigate ground water contamination by benzo(a)pyrene
 - > Establish RL and associated precision & bias
 - Select analytical method & contract lab
- Inputs:
 - > **AL**: 0.2 ppb (MCL)
 - Anticipated Data Quality: RSD = 9.5% & %R = 81% (DoD QSM LCS)
 - > Tolerable Decision Errors: FP = FN = 5%
- $RL \le (AL 4 \times RSD \times AL) \times \%R = 0.10 ppb$
 - \rightarrow if RSD \leq 9.5% & %R \geq 81%

Case Study of Method & Lab Selections

- LOQ ≤ RL ≤ (AL 4 × RSD × AL) × %R = 0.10 ppb
 if AL = 0.2 ppb, RSD ≤ 9.5% & %R ≥ 81%
- DoD ELAP accredited Lab X:
- > SW 8270: LOQ = 0.2 ppb, RSD = 16.2% & %R = 82.5% (Ideally, LOQ \leq (0.2 4 × 16.2% × 0.2) × 82.5% = 0.058 ppb)
 - DoD ELAP accredited Lab Y:
- \searrow > SW 8270: LOQ = 0.2 ppb, RSD = 9.8% & %R = 84.5%
- \checkmark > SW 8310: LOQ = 0.1 ppb, RSD = 9.5% & %R = 92.5%

Relationships among Various Limits



Major Issues

- 1. Old Rule of Thumb, RL = 1/2 ~ 1/5 AL, may not be adequate
- 2. LOQ ≤ RL is neither necessary nor sufficient; lower LOQ is not necessary better must consider precision & bias at LOQ and RL
- 3. RL based on precision & bias of clean matrix spikes is a minimum RL
- 4. Safety factors built in AL or risk assessment do not take care of decision errors
- 5. Huge field sampling errors trump lab analysis errors

Old Rule of Thumb, RL = 1/2 ~ 1/5 AL, may not be adequate

If AL = 100, is $RL = 50 \sim 20$ adequate?

$$>$$
 Ideal SW-846 default, LCS CL = 70 − 130% (RSD = 10% & %R = 100%) and $α = β = 0.05$ (k = 4)

RL
$$\leq$$
 (AL - k × RSD × AL) × %R
 \leq (100 - 4 × 10% × 100) × 100% = 60
1/2 ~ 1/5 AL = 50 ~ 20 < 60

$$\rightarrow$$
 If LCS CL = 20 - 80% (RSD = 10% & %R = 50%)

$$RL \le (100 - 4 \times 10\% \times 100) \times 50\% = 30$$


$$1/2 AL = 50 > 30$$

$$1/2 \text{ AL} = 50 > 30$$
 $1/5 \text{ AL} = 20 < 30$





LOQ ≤ RL is neither necessary nor sufficient; Lower LOQ is not necessary better – must consider P&B



RL based on precision & bias of clean matrix spikes is a minimum RL

- Precision & bias based on clean matrix spikes such as method performance data, DoD QSM, or lab's LCS do not include matrix interferences
- A common denominator approach similar to DL, QL, and LCS studies for data comparability
- Because individual matrices are different, matrixspecific precision & bias cannot be reliably and cost-effectively estimated prior to sample analysis
- Matrix interferences may be assessed upon sample receipt or based on MS/MSD



Safety factors built in AL or risk assessment do not take care of decision errors

- To have or not to have corrective action generally depends on the data quality and tolerable decision errors at the AL, not the accuracy of the AL
- Safety factors may not affect the decision rule, e.g., if [X] > AL, clean site; if [X] ≤ AL, dirty site
- To reliably determine if [X] > AL, one needs to quantify and make the decision at RL



Huge field sampling errors trump lab analysis errors

- Lab shall meet project MQOs, not DQOs. Lab is not liable for sampling errors and can't compensate large sampling uncertainty (Typical lab RSD must be < 25%)</p>
- Field sampling uncertainty cannot be reliably estimated without site investigation and is typically > 4x lab uncertainty
- Lab performance yardsticks, method performance data, do not include field sampling uncertainty
- Need better sampling techniques (e.g., MIS) to reduce and control field sampling errors prior to evaluating field sampling uncertainty

Summary

- A simple, reliable, and practical procedure for establishing RL based on project-specific AL, anticipated data quality, and tolerable decision errors
- RL established based on precision and bias of clean matrix spikes is a minimum RL. More stringent RL is needed to cover sample matrix interferences and field sampling errors
- A useful tool for project planning, selecting analytical methods and contract labs prior to contract award
- LOQ ≤ RL < AL may not meet project DQOs



For more information, please contact:

Chung-Rei Mao



Phone: 402-697-2570

e-mail: chung-rei.mao@usace.army.mil



Questions?

